

# Grinchmas Ornaments

featuring *How the Grinch Stole Christmas*  
by Dr. Seuss Enterprises

## Supplies needed:

- 1 panel - ADE-13671-223
- 1/8 yd - ADE-13672-223
- 1/8 yd - ADE-13672-240
- 1/8 yd - ADE-13673-63
- 1/8 yd - ADE-13673-223
- 1/8 yd - ADE-13674-223
- 1/8 yd - ADE-13675-63
- 1/4 yd - ADE-13672-63
- 7/8 yd - Kona Cotton Poppy
- 7/8 yd - Kona Cotton - Papaya
- 7/8 yd - Kona Cotton Cloud
- 5 yards - ADE-13675-240
- Backing : 5 yards

## Pattern Level: Confident Beginner


*"I have basic block construction down  
and would like to learn a new trick!"*



Finished Size: 74" x 84"

## Instructions:

- 1) Cut the Grinch Panel into 15 8" squares.
- 2) From 7 coordinating prints, cut four 2"x8" pieces and four 2" x 11" pieces. The most efficient way to cut these pieces is to cut two 2" x WOF strip, then cut two 11" pieces, and two 8" pieces from each strip. From the 8th coordinating print, cut two 2" x 8" pieces and four 2" x 11" pieces and cut 15 ornament tops (2" x 4").
- 3) Sew the 8" pieces to the sides of the panel squares, then sew the 11" pieces to the tops and bottoms of the squares. Press.
- 4) From the three solids: subcut into eight WOF x 3" strips. From each color, cut ten 3"x11" pieces and ten 3" x 16" pieces. The most efficient way to cut these pieces is to cut two 16" pieces from five strips, cut one 11" piece from the ends of each of those five strips, then cut the remaining five 11" pieces needed from the last three strips.
- 5) Sew the 3" x 11" pieces to the sides of the squares, and the 3" x 16" pieces to the tops and bottoms.
- 6) Following the directions on your fusible web, trace the circle template to make 15 circles with 15" diameter. Attach the fusible web to the back of the ornament squares and cut out the circles.
- 7) From the scraps of your fusible web, cut 15 ornament tops (2" x 4"), and apply to the fabric tops.
- 8) From the backing and background fabrics, trim off the selvages, then cut the 5yds in half to get 2 pieces 2.5yds long. Sew together along the short sides to make a large piece 88" wide x 90" long.
- 9) Placing your background fabric on a design wall or floor, arrange the ornaments as desired and pin in place. Following the directions of your fusible web, iron the ornaments to adhere them to the background fabric. Repeat to attach the ornament tops. You can either sew the ornaments down to the quilt background now, or you can make a quilt sandwich, baste it, and sew down the ornaments and tops while quilting.



## Template Piece