

Woodland Glow

Designed by Robert Kaufman Fabrics


Featuring: Woodland Glow
by Russell Cobane



Finished Quilt Measures: 32" x 39"

ROBERT KAUFMAN
F A B R I C S

Fabric and Supplies Needed

Color	Fabric	Name/SKU	Yardage	Color	Fabric	Name/SKU	Yardage
	A	ARK-17542-223 HOLIDAY	2/3 yd		C	ETJ-9864-289 LT. BLUE	1/4 yd
	B	ETJ-9864-213 TEAL	2/3 yd		Binding	ETJ-9864-91 CRIMSON	1/3 yd

You Will Also Need:
1-3/8 yards Backing Fabric

Notes Before You Begin

- Please read through all of the instructions before beginning.
- All of the seam allowances are 1/4" unless otherwise noted.
- Width of fabric (WOF) is equal to at least 42" wide.
- Press all seam allowances open after each seam is sewn, unless otherwise noted.
- Remember to measure twice and cut once!

Cutting Instructions

Fabric A

Fussy cut the following blocks from the panel:

Tree block: 12-1/2" wide x 21-1/2" tall

Donkey, barn, horse, and deer blocks: 12-1/2" wide x 10-1/2" tall

Fabric B

Cut five strips 1-1/2" x WOF - for sashing

from one strip sub cut three strips 1-1/2" x 12-1/2"

trim two strips down to 1-1/2" x 27-1/2"

trim three strips down to 1-1/2" x 32-1/2"

Cut four strips 2-1/2" x WOF

trim two strips down to 2-1/2" x 32-1/2" - for top and bottom outer borders

trim two strips down to 2-1/2" x 35-1/2" - for side outer borders

Fabric C

Cut four strips 1" x WOF

trim two strips down to 1" x 34-1/2" - for side inner borders

trim two strips down to 1" x 28-1/2" - for top and bottom inner borders

Binding:

Cut four strips 2-1/2" x WOF

Block Construction

Step 1: Sew a 1-1/2" x 12-1/2" Fabric B sashing strip between three of the 10-1/2" x 12-1/2" panels to make one long block (see fig. 1). Press towards sashing.




fig. 1



Step 2: Sew a 1-1/2" x 12-1/2" Fabric B sashing strip between the 12-1/2" x 21-1/2" Tree Block and the remaining 10-1/2" x 12-1/2" block (See fig. 2). Press towards Sashing.



fig. 2

Step 3: Sew a 1-1/2" x 32-1/2" Fabric B sashing strip between and on either side of the block columns from Steps 1 and 2. Press towards sashing. Sew a 1-1/2" x 27-1/2" Fabric B sashing strip to the top and bottom of the quilt top. See diagram to the right. Press towards sashing.



Step 4: Following the quilt assembly diagram sew the 1" x 34-1/2" Fabric C side inner borders to the quilt top. Press towards sashing.

Step 5: Sew the 1" x 28-1/2" Fabric C top and bottom inner borders to the quilt top. Press towards sashing.

Step 6: Following the quilt assembly diagram sew the 2-1/2" x 35-1/2" Fabric B side outer borders to the quilt top. Press towards sashing.

Step 7: Sew the 2-1/2" x 32-1/2" Fabric B top and bottom outer borders to the quilt top. Press towards sashing.

Step 8: Your quilt top is now complete. Sandwich baste and quilt using your favorite method. Bind in binding fabric.

