

JINGLE JANGLE STOCKINGS

Designed by Ramona Rose
www.ramonarose.net

Featuring

JINGLE

BY

Ann Kelle



Finished project measures: 12" x 10"

Materials listed in this pattern are enough to make four stockings.

Pattern Level: Enthusiastic Novice






"I am a total beginner and want to learn more!"

ROBERTKAUFMAN
F A B R I C S



For questions about this pattern, please email Patterns@RobertKaufman.com.

Fabric and Supplies Needed for Four Stockings

Fabric amounts based on yardage that is 40" wide.

Color	Fabric	Name/SKU	Yardage	Color	Fabric	Name/SKU	Yardage
	A	AAK-15912-223 HOLIDAY	2/3 yard (1 panel)		D	AAK-15906-3 RED	3/4 yard
	B	AAK-15907-11 ROYAL	3/4 yard		E	AAK-15907-70 AQUA	3/4 yard
	C	AAK-15906-2 BLACK	3/4 yard	<div>You will also need: 3-3/4 yards for backing</div>			
Copyright 2016, Robert Kaufman For individual use only - Not for resale							

OR

Color	Fabric	Name/SKU	Yardage	Color	Fabric	Name/SKU	Yardage
	A	AAK-15912-223 HOLIDAY	2/3 yard (1 panel)		B	PRINT FABRIC OF YOUR CHOICE	3 yards
Copyright 2016, Robert Kaufman For individual use only - Not for resale				<div>You will also need: 3-3/4 yards for backing</div>			

Notes Before You Begin

- Read through all of the instructions before beginning.
- All of the seam allowances are 1/4" unless otherwise noted.
- Press seam allowances open unless otherwise noted.
- Width of fabric (WOF) is equal to at least 40" wide.
- Right sides together has been abbreviated to RST.
- Remember to measure twice and cut once!

Cutting Instructions

From Fabric A, cut:

stockings and cuffs (cut each on the lines printed on the panel)

Note: the Fabric A pieces will now become the templates you'll use to cut the Fabric B-E pieces.

From each of Fabrics B-E, cut:

one stocking


two stockings REVERSED

three cuffs


one 2" x 10" rectangle for a hanging loop

Assemble the Stockings

Step 1: Place a stocking piece and a Fabric B stocking right sides together. Sew together, using a 5/8" seam allowance and backstitching at each end. Leave the top unsewn. It is important to be sure you are sewing on the edge of the stocking panel print, so you don't leave a white border when the stocking is turned right side out. *Tip: Shorten the stitch length on your machine to aid in sewing the curves.*




Step 2: Repeat Step 1 for the lining, using two remaining Fabric B pieces. This time, leave a 3" opening on the side of the lining for turning later. Backstitch at the both ends of each seam.





Step 3: Trim the seam allowance on the stocking and lining to 1/4", and then clip the seam allowance at the curves, taking care not to clip the stitching.

Step 4: Place a cuff and a Fabric B piece right sides together. Sew along both short sides, using a 5/8" seam allowance. Press the side seams open. Repeat for the lining pieces.



Step 5: Fold the hanging loop RST in half along the length (matching the 10" sides). Sew along the raw edge with a 3/8" seam, backstitching at each end. Trim the seam allowance to a scant 1/4" and turn the tube right side out using a safety pin or turning tool. Press. Align the raw ends of the tube and baste together.

Step 6: Pin the basted loop on the back seam of the stocking lining, so that the loop hangs down into the lining. Baste it in place. Adjust the length as desired.



Step 7: Place the one cuff inside the other, RST, and matching the side seams. Sew around the bottom of the cuff, following the printed edge of the Fabric A piece (not sewing on the white border). Turn the cuff right side out and press the seam flat. Baste around the top edge of the cuff using a 1/4" seam allowance.

Step 8: Place the cuff around the main body of the stocking exterior, with the Fabric A cuff facing out and aligning the raw edges of the stocking opening and the cuff. Pin. Baste the cuff in place around the opening with a 1/4" seam allowance.



Step 9: Turn the lining piece wrong side out. Insert the main stocking/cuff unit inside the lining. The right sides of the stockings should be together and the cuff and hanging loop should be sandwiched between the two stockings. Pin around the opening and sew around the opening, using a 5/8" seam (following the printed edge of the stocking and cuff).

Step 10: Turn the stocking right side out through the opening in the lining. Tuck the raw edges of the opening in and sew the opening closed.

Step 11: Push the lining into the stocking, then fold down the cuff and pull out the hanging loop. Give the stocking a good press again, then find a chimney with a hook and wait for Santa!